

TI-99/4 Extended BASIC Reference Card

A handy guide to the commands, statements, and functions of TI Extended BASIC for the TI-99/4 Home Computer. For a full discussion of these and other features, see the TI Extended BASIC manual.



C: COMMAND F: FUNCTION S: STATEMENT

- ABS**(*numeric-expression*)
returns the absolute value of *numeric-expression*. **F**
- ACCEPT** [[*AT*(*row,column*)] [**VALIDATE** (*datatype* ...)]
[**BEEP**] [**ERASE ALL**] [**SIZE**(*numeric-expression*)]
: *variable*
suspends program execution until data is entered from the keyboard. Optionally, data is entered at the position specified by *row* and *column*, the data is validated, and/or option(s) are executed. **S,C**
- VALIDATE** *datatypes*:
L:ALPHA permits all uppercase alphabetic characters.
D:DIGIT permits 0 through 9.
N:NUMERIC permits 0 through 9, ., +, -, *, /, %, ^, and 'E'.
String-expression permits the characters contained in *string-expression*.
BEEP: causes an audible tone.
ERASE ALL: places the space character in all screen positions before accepting input.
SIZE(*numeric-expression*): allows only *numeric-expression* characters to be entered. If *numeric-expression* is positive, that many positions are blanked. If it is negative, no positions are blanked.
- ASC**(*string-expression*:*i*)
returns the ASCII code of the first character of *string-expression*. **F**
- ATN**(*numeric-expression*)
returns the trigonometric arctangent of *numeric-expression*. **F**
- BREAK** [*line-number-list*]
causes program to halt when encountered or optionally, when lines in *line-number-list* are encountered. **C,S**

BYE
closes open files and leaves TI Extended BASIC. **C**

CALL SUBPROGRAM [(parameter-list)]
calls the indicated subprogram. An optional parameter-list can be passed. **S**

CALL CHAR(character-code, pattern-identifier [...])
defines the specified ASCII character code(s) using a 0 through 64 character hexadecimal coded string pattern-identifier. **S,C**

CALL CHARPAT(character-code, string-variable [...])
returns in string-variable the hexadecimal code that specifies the pattern of character-code. **S,C**

CALL CHARSET
restores the standard character patterns and colors for characters 32 through 95. **S,C**

CHR\$(numeric-expression)
returns the string character corresponding to the ASCII numeric-expression. **F**

CALL CLEAR
places the space character in all screen positions. **S,C**

CLOSE #file-number [:DELETE]
stops the program's use of the file referenced by #file-number and optionally deletes the file. **S,C**

CALL COINC(#sprite-number, #sprite-number, tolerance, numeric-variable)
tolerance, numeric-variable

CALL COINC(#sprite-number, dot-row, dot-column, tolerance, numeric-variable)
tolerance, numeric-variable

CALL COINC(ALL, numeric-variable)
returns in numeric-variable -1 if there is a coincidence and 0 if there is no coincidence. If ALL is present, a coincidence of any two sprites is reported. If two sprites are identified by number, their coincidence is reported. If a sprite and a position are identified, their coincidence is reported. Except when ALL is specified, a tolerance of from 0 to 255 is specified. The distance between the given sprites or sprite and position must be less than tolerance for a coincidence to be reported. **S,C**

CALL COLOR(#sprite-number, foreground-color [...])
CALL COLOR(character-set, foreground-color, background-color [...])
specifies either a color for #sprite-number or a foreground-color and background-color for characters in character-set. **S,C**

CONTINUE
CON
resumes execution after a break. **C**

COS(radian-expression)
returns the trigonometric cosine of radian-expression. **F**

DATA data-list
stores numeric and string constant data in program. **S**

DEF function-name [(parameter)] = expression
associates user-defined numeric or string expression with function-name. **S**

DELETE device-filename
removes filename from device. **C,S**

CALL DELSPRITE(#sprite-number [...])
CALL DELSPRITE(ALL)
removes the specified sprite(s) from the screen. **ALL**
removes all sprites from the screen. **S,C**

DIM array-name(integer1 [,integer2] ... [,integer7]) [...]
dimensions the listed array(s) as specified. **S,C**

DISPLAY [AT:row:column] [BEEP] [ERASE ALL, SIZE(numeric-expression)] [: variable-list]
transfers variable-list to the display screen. Optionally, data is displayed at the position specified by row and column. **S,C**
Options:
BEEP: causes an audible tone.
ERASE ALL: places the space character in all screen positions before displaying.
SIZE numeric-expression: blanks numeric-expression characters in the indicated position.

DISPLAY [option-list:] USING string-expression
[: variable-list]

DISPLAY [option-list:] USING line-number [: variable-list]
has the same options as **DISPLAY** with the addition of
the USING clause, which specifies the format. If
string-expression is present, it defines the format. If
line-number is present, it refers to the line number of
IMAGE statement. See **IMAGE**, **S,C**

CALL DISTANCE(#sprite-number, #sprite-number,
numeric-variable)

CALL DISTANCE(#sprite-number.dot-row.dot-column,
numeric-variable)

returns in numeric-variable the square of the distance
between the sprites or the sprite and the location. **S,C**

END

terminates program execution. **S**

EOF(file-number)

returns the end-of-file condition of file-number. **F**

0: not end-of-file.

1: logical end-of-file.

- 1: physical end-of-file.

CALL ERR(error-code,error-type [,error-severity,line-
number])

returns the error-code and error-type of the most
recent uncleared error. Optionally, returns the error-
severity and line-number in which the error occurred.

S,C

Error-code: consult manual.

Error-type: Negative number: execution error. Positive

number: number of file in which the error occurred.

Error-severity: 9, indicating that the error is not

recoverable.

EXP(numeric-expression)

returns exponential value (e^x) of numeric-expression.

The value of e is 2.718281828. **F**

FOR control-variable = initial-value TO limit [STEP
increment]

repeats execution of statements between **FOR** and
NEXT until the control-variable exceeds the limit.
STEP increment default is one. **S,C**

CALL GCHAR(row,column,numeric-variable)

returns in numeric-variable the ASCII code of the
character located at row and column. **S,C**

GOSUB line-number

GO SUB line-number

transfers control to a subroutine at line-number. **S**

GOTO line-number

GO TO line-number

unconditionally transfers control to line-number. **S**

CALL HCHAR(row,column,character-code [,repetition])

places the ASCII pattern of character-code at row and
column and optionally repeats it repetition times
horizontally. **S,C**

IF relational-expression THEN line-number1 [ELSE line-
number2]

IF relational-expression THEN statement1 [ELSE
statement2]

IF numeric-expression THEN line-number1 [ELSE line-
number2]

IF numeric-expression THEN statement1 [ELSE
statement2]

transfers control to line-number1 or performs

statement1 if relational-expression is true or

numeric-expression is not equal to zero. Otherwise

control passes to the next statement, or optionally to

line-number2 or statement2. **S**

IMAGE format-string

specifies the format in which data is PRINTed or
DISPLAYed when the USING clause is present.

Format-string may be any or all of the following:

Letters, numbers, characters not listed below:

 : transferred directly.

 #: replaced by the print-list values given in **PRINT**

 or **DISPLAY**.

 A: replaced by the E and power numbers. Must be

 four or five of these. **S**

CALL INIT

prepares the computer to load and run assembly language subprograms. **S,C**

INPUT [*input-prompt*[:] *variable-list*]

suspends program execution until data is entered from the keyboard. The optional *input-prompt* may indicate what data is expected. **S**

INPUT *#file-number* [**REC record-number**] :*variable-list*
 assigns data from the indicated file to the variables in *variable-list*. Records are read sequentially unless the optional **REC** clause is used. **S**

INT(*numeric-expression*)

returns the greatest integer less than or equal to *numeric-expression*. **F**

CALL JOYST(*key-unit*,*x-return*,*y-return*)

accepts data into *x-return* and *y-return* based on the position of the joystick labeled *key-unit*. Values are -4, 0, and 4. **S,C**

CALL KEY(*key-unit*,*return-variable*,*status-variable*)

assigns the code of the key pressed on *key-unit* (0 to 5) to *return-variable*. Status information is returned in *status-variable*. 1 means a new key was pressed. -1 means the same key was pressed. 0 means no key was pressed. **S,C**

LEN(*string-expression*)

returns the number of characters in *string-expression*.

F

[LET] *numeric-variable* [= *numeric-variable*, ...]

= *numeric-expression*

[LET] *string-variable* [= *string-variable*, ...] = *string-expression*

assigns the value of an expression to the specified variable(s). **S,C**

CALL LINK(*subprogram-name* [,*argument-list*])

passes control to an assembly language subprogram. **S,C**

LINPUT [[*#file-number*] | **REC record-number**] : *string-variable*

LINPUT [*input-prompt*[:] *string-variable*]

assigns data from the indicated file to *string-variable* or suspends program execution until data is entered from the keyboard. If data is assigned from a file, records are read sequentially unless the optional **REC** clause is used. If data is entered from the keyboard, the optional *input-prompt* may indicate what data is expected. **S**

LIST ["device-name" :] [*line-number*]

LIST ["device-name" :] [*start-line-number*] - [*end-line-number*]

sequentially displays program statements or optionally a single line number or all lines between specified line numbers. **C**

CALL LOAD ["access-name" :] [*address.byte1* [...]] / *file-field*, ...]

loads an assembly language subprogram. **S,C**

CALL LOCATE(*#sprite-number*,*dot-row*,*dot-column* [...])

moves the given sprite(s) to the given *dot-row(s)* and *dot-column(s)*. **S,C**

LOG(*numeric-expression*)

returns the natural logarithm of *numeric-expression*.

F**CALL MAGNIFY**(*magnification-factor*)

sets the size and magnification of all sprites. **S,C**

Magnification-factors:

1: single size unmagnified.

2: single size magnified.

3: double size unmagnified.

4: double size magnified.

MAX(*numeric-expression1*,*numeric-expression2*)

returns the larger of *numeric-expression1* and *numeric-expression2*. **F**

MERGE ["] *device-filename* ["]

merges lines in *filename* from the given *device* into the program lines already in the computer's memory.

C

MIN(*numeric-expression1*, *numeric-expression2*)
 returns the smaller of *numeric-expression1* and *numeric-expression2*. **F**

CALL MOTION(*#sprite-number*, *row-velocity*, *column-velocity* [...])
 changes the motion of a sprite(s) to the indicated *row-velocity* and *column-velocity*. **S,C**

NEW
 clears the memory and screen and prepares for a new program. **C**

NEXT *control-variable*
 See FOR statement. **S,C**

NUMBER [*initial-line*] [*increment*]
NUM [*initial-line*] [*increment*]
 generates sequenced line numbers starting at 100 in increments of 10. Optionally, you may specify the *initial-line* and/or *increment*. **C**

OLD [''] *device-program-name* ['']
 loads *program-name* from *device* into memory. **C**

ON BREAK STOP
ON BREAK NEXT
 determines the action taken if a breakpoint is encountered either in the program or by **SHIFT C** (CLEAR). The default is STOP, which halts execution of the program. The keyword **NEXT** causes breakpoints to be ignored and execution of the program to continue. **S**

ON ERROR STOP
ON ERROR *line-number*
 determines the action taken if an error occurs. The default is STOP, which halts execution of the program. If *line-number* is given, control is transferred to it when an error occurs. See RETURN. **S**

ON numeric-expression GOSUB *line-number* [...]
ON numeric-expression GO SUB *line-number* [...]
 transfers control to the subroutine with a beginning line number in the position corresponding to the value of *numeric-expression*. **S**

ON numeric-expression GOTO *line-number* [...]
ON numeric-expression GO TO *line-number* [...]
 unconditionally transfers control to the line number in the position corresponding to the value of *numeric-expression*. **S**

ON WARNING PRINT
ON WARNING STOP
ON WARNING NEXT
 determines the action taken if a warning condition occurs. The default is PRINT, which prints a message and continues with the program. The keyword **STOP** causes the warning message to be printed and execution of the program to stop. The keyword **NEXT** causes no message to be printed and the program to continue. **S**

OPEN *#file-number*: "*device:filename*" [*file-organization*] [*file-type*] [*open-mode*] [*record-type*]
 enables the program to use the given *filename*. **S,C**

File-number: 0-255
File-organization: RELATIVE or SEQUENTIAL.
File-type: DISPLAY or INTERNAL.
Open-mode: INPUT, OUTPUT, UPDATE, or APPEND.
Record-type: FIXED or VARIABLE.

OPTION BASE 0
OPTION BASE 1
 sets the lowest allowable subscript of arrays to zero or one. The default is zero. **S**

CALL PATTERN(*#sprite-number*, *character-value* [...])
 changes the pattern number of the specified sprite(s) to the specified *character-value(s)*. **S,C**

CALL PEEK(*address*, *numeric-variable-list*)
 returns values in *numeric-variable-list* corresponding to the values in *address*. **S,C**

PI
 returns the value of pi as 3.14159265359. **F**

POS(*string1*, *string2*, *numeric-expression*)
 returns the position of the first occurrence of *string2* in *string1*. Search begins at the position specified by *numeric-expression*. Returns zero if no match is found. **F**

CALL POSITION(*#sprite-number*,*dot-row*,*dot-column* [,...])
returns the positions in the given *dot-row(s)* and *dot-column(s)* of the specified *sprite(s)*. **S,C**

PRINT [*#file-number* [,*REC record-number*] :] [*print-list*]
transfers optional *print-list* to the display screen or optionally to an external file. The *REC* clause directs *print-list* to the specified *record-number*. **S,C**

PRINT [*#file-number* [,*REC record-number*]] **USING** *string-expression*:*print-list*

PRINT [*#file-number* [,*REC record-number*]] **USING** *line-number*:*print-list*

acts the same as **PRINT** with the addition of the *USING* clause, which specifies the format. If *string-expression* is present, it defines the format. If *line-number* is present, it refers to the line number of an *IMAGE* statement. See *IMAGE*. **S,C**

RANDOMIZE [*numeric-expression*]
resets the random number generator to an unpredictable sequence. With optional *numeric-expression*, the sequence is repeatable. **S,C**

READ *variable-list*
assigns numeric and string constants from *DATA* statements to *variable-list*. **S,C**

REC(*file-number*)
returns the current record position in *file-number*. **F**

REM *character-string*
indicates internal program documentation with no effect on program execution. **S,C**

RESEQUENCE [*initial-line*] [,*increment*]

RES [*initial-line*] [,*increment*]
automatically renumbers lines starting at 100 in increments of 10. Optionally, you may specify the *initial-line* and/or *increment*. **C**

RESTORE [*line-number*]
indicates that the next **READ** operation will take data from the first *DATA* statement in the program or, optionally, from the first *DATA* statement after *line-number*. **S,C**

RESTORE *#file-number* [,*REC record-number*]
resets file pointer to the beginning of the file or, optionally, to *record-number*. **S,C**

RETURN
transfers program control from a subroutine to the statement following the corresponding **GOSUB** or **ON...GOSUB** statement. **S**

RETURN [*line-number*]

RETURN [**NEXT**]

controls program action after an error has occurred when an **ON ERROR** statement has been executed. With nothing following it, returns control to the statement which caused the error and executes it again. Followed by a *line-number*, it transfers control to the given line. Followed by **NEXT**, it transfers control to the statement after the one in which the error occurred. **S**

RND
generates a pseudo-random number greater than or equal to zero and less than one. **F**

RPTS(*string-expression*,*numeric-expression*)
returns *numeric-expression* occurrences of *string-expression* concatenated together. **F**

RUN ["*device*,"*program-name*"]

RUN [*line-number*]

starts program execution at the lowest program statement of the program currently in memory. Optionally *program-name* is loaded from *device* or execution starts at *line-number*. **C,S**

SAVE *device* *program-name* [,**PROTECTED**]

SAVE *device* *program-name* [,**MERGE**]

places a copy of the current program in *device* as *program-name*. **PROTECTED** makes it impossible to change or list the program later. **MERGE** enables later merging of the program with another program. See **MERGE**. **C**

CALL SAY(*word-string* [,*direct-string*] [,...])

causes the speech synthesizer to speak the given *word-string* or *direct-string*. **S,C**

CALL SCREEN(*color-code*)

changes the screen color to *color-code*. **S,C**

SEGS(*string-expression*,*position*,*length*)

returns a substring of *string-expression* beginning at *position* and extending for *length* characters. **F**

SGN(*numeric-expression*)
returns 1 if *numeric-expression* is positive, 0 if it is zero, and -1 if it is negative. **F**

SIN(*radian-expression*)
returns the trigonometric sine of *radian-expression*. **F**

SIZE
displays on the screen the number of unused bytes of memory. **C**

CALL SOUND(*duration*,*frequency1*,*volume1* [*....*],*frequency4*,*volume4*)
controls up to three tone and one noise generators. Tone and noise parameters can occur in any order. Negative duration causes immediate sound update. **S,C**
Duration: 1 through 4250 ms., -4250 through -1 ms.
Frequency: 110 through 44733 Hz for tone, -1 through -8 for noise.
Volume: 0 (loudest) through 30 (softest).

CALL SPGET(*word-string*,*return-string*)
returns in *return-string* the speech bit pattern that corresponds to *word-string*. **S,C**

CALL SPRITE(*#sprite-number*,*character-value*,*sprite-color*,*dot-row*,*dot-column*, [*row-velocity*, *column-velocity*] [*....*])
specifies the existence of *sprite(s)* *sprite-number* with a pattern specified by *character-value*, a color of *sprite-color*, a screen position of *dot-row* and *dot-column*, and optionally a velocity of *row-velocity* and *column-velocity*. **S,C**

SQR(*numeric-expression*)
returns the square root of *numeric-expression*. **F**

STOP
terminates program execution. **S,C**

STR\$(*numeric-expression*)
converts the value of *numeric-expression* to a string. **F**

SUB *subprogram-name* [(*parameter-list*)]
indicates the beginning of *subprogram-name* with optional *parameter-list*. **S**

SUBEND
indicates the end of a subprogram and transfers program control from a subprogram to the statement following the CALL statement. **S**

SUBEXIT
transfers program control from a subprogram to the statement following the CALL statement. **S**

TAB(*numeric-expression*)
controls column position of the output from a PRINT or DISPLAY statement. **F**

TAN(*radian-expression*)
returns the trigonometric tangent of *radian-expression*. **F**

TRACE
lists line numbers of lines before each is executed. **C,S**

UNBREAK [*line-list*]
removes all breakpoints or optionally those in *line-list*. **C,S**

UNTRACE
cancels the action of the TRACE command. **C,S**

VAL(*string-expression*)
converts *string-expression* into a numeric constant. **F**

CALL VCHAR(*row*,*column*,*character-code* [*repetition*])
places the ASCII representation of *character-code* at *row* and *column* and optionally repeats it *repetition* times vertically. **S,C**

CALL VERSION(*numeric-variable*)
returns a value indicating the version of BASIC being used. TI Extended BASIC returns a value of 100. **S,C**

Character Sets		
Set	ASCII Codes	Set ASCII Codes
0	30-31	
1	32-39	88-95
2	40-47	96-103
3	48-55	104-111
4	56-63	112-119
5	64-71	120-127
6	72-79	128-135
7	80-87	136-143

Color Codes

Color	Code	Color	Code
Transparent	1	Medium Red	9
Black	2	Light Red	10
Medium Green	3	Dark Yellow	11
Light Green	4	Light Yellow	12
Dark Blue	5	Dark Green	13
Light Blue	6	Magenta	14
Dark Red	7	Gray	15
Cyan	8	White	16

ASCII Code	Character	ASCII Code	Character
30	(cursor)	63	(question mark)
31	(edge character)	64	@ (at sign)
32	(space)	65	A
33	! (exclamation point)	66	B
34	" (quote)	67	C
35	# (number or pound sign)	68	D
36	\$ (dollar)	69	E
37	% (percent)	70	F
38	& (ampersand)	71	G
39	' (apostrophe)	72	H
40	((open parenthesis)	73	I
41) (close parenthesis)	74	J
42	* (asterisk)	75	K
43	+ (plus)	76	L
44	, (comma)	77	M
45	- (minus)	78	N
46	. (period)	79	O
47	/ (slash)	80	P
48	0	81	Q
49	1	82	R
50	2	83	S
51	3	84	T
52	4	85	U
53	5	86	V
54	6	87	W
55	7	88	X
56	8	89	Y
57	9	90	Z
58	: (colon)	91	[(open bracket)
59	; (semicolon)	92	\ (reverse slash)
60	< (less than)	93] (close bracket)
61	= (equals)	94	^ (exponentiation)
62	> (greater than)	95	_ (underline)

The following key presses may also be detected by CALL KEY.

1	SHIFT A	3	SHIFT F
4	SHIFT G	6	SHIFT R
7	SHIFT T	8	SHIFT S
9	SHIFT D	10	SHIFT X
11	SHIFT E	12	SHIFT V
13	ENTER	14	SHIFT W
15	SHIFT Z		